A guide to setting Up Nexmo Transport on the Core and with the Userportal as the client. First deploy the core on your local server. Once running open the server tab and add a new server

<u>Status</u> Log Viewer	Transport>General 👳
© Server © Policy	Please enter the details for the various transports. Transports are used to send security strings and alerts to users. To enable one complete all the available field Warning: Changing the identifier of a transport that is in use will result in the loss of configuration and any queued messages.
E Logging E transport • User Adrts • Disc Adrts • Disc Adrts • Inbound STOP • exstInations • Inbound STOP • exstInations B Mode B Mo	Transports:          Y wice          SMI2          SMI2         GMM balance          SMI2 <tr< td=""></tr<>

Next we need to setup some of the NexMoVoice transport attributes, under Transport/NexmoVoice.

<u>Status</u>	Transport>NexmoVoice					
Log Viewer						
Server	[transport_nexmo_intro]					
Policy						
	[transport_nexmo_timeout]:	180000				
Transport <u>General</u> User Alerts	[transport_nexmo_prompt]:	/our one-time code:bye				
Provisioning     Inbound STOP	[transport_nexmo_nexmomessageurl]:	rest.nexmo.com/tts/xml				
<u>syedTransport</u> <u>NexmoVoice</u>	[transport_nexmo_nexmoprompturl]:	mo.com/tts-prompt/xml				
⊞ Database	[transport_nexmo_nexmocallback]:	)/pinsafe/nexmoinbound				
Repository	[transport_nexmo_nexmoapikey]:	9add5bc5				
<ul> <li>■ RADIUS</li> <li>■ Migration</li> </ul>	[transport_nexmo_nexmoapisecret]:	•••••				
Appliance	[transport_nexmo_nexmodigits]:	4				
Synchronisation Administration     Reporting <u>User Administration</u> <u>Save Configuration</u>	[transport_nexmo_credentialsmsg]:	Your new PINsafe credentials are:%CR%LFUsername: %NAME%CR %LFPassword: %PASSWORD%CR%LFPIN: %PIN				
Administration Guide     Logout	[transport_nexmo_codesheader]:	r]: PINsafe One Time Code Message %NUMBER%CR%LF%OTC				
	[transport_nexmo_stringsheader]:	PINsafe Security String Message %NUMBER%CR%LF%STRING				
	[transport_nexmo_stringheader]:	Yes •				
	[transport_nexmo_stringdelimiter]:					
	[transport_nexmo_verticalstrings]:	No 🕶				
	[transport_nexmo_pinexpirymsg]:	Your PIN is set to expire in %DAYS days. If you do not change your PIN before it expires you will no longer be permitted to log in.				
	[transport_nexmo_pinchangerequiredmsg]:	You are now required to change your PIN. If you do not change your PIN at this time you will not be permitted to log in on subsequent attempts.				
	[transport_nexmo_pinchangedmsg]:	Your PINsafe PIN was changed at %TIME on %DATE. If you did not perform this change please contact your system administrator immediately.				
		Your PINsafe account has been locked. Please contact your system				

## Here Here's what we set:

Attribute	Value	Explanation
timeout	180000	The timeout
		allowed for a
		request
prompt	Enter your one-time code:bye	What is said to the
		user by Nexmo
nexmomessageurl	https://rest.nexmo.com/tts/xml	Text to speech url
		on nexmo servers
nexmoprompturl	https://rest.nexmo.com/tts-prompt/xml	A message to
		prompt user to say
		something
nexmocallback	http://83.105.30.10:8080/pinsafe/nexmoinb	Call back url calling
	ound	our nemoinbound

		object
Nexmoapikey	9add5bc5	Api key
Nexmoapisecret	******** (Ask Chris or Syed)	Api password

next configuration for the swivel core is to configure the dual channel for the new voice transport we have just added. Open the Server/Dual channel

There are 2 RULES for voice transport channel. Match and Message

**MATCH**: When In Bound OTC rule on the dual channel config page is set to **MATCH** then the OTC field on the user portal should be set to the users OTC (not the long session id auto populated) and also the user should enter the same OTC into the phone when prompted. **MESSAGE**: When In Bound OTC rule on the dual channel config page is set to **MESSAGE** then the OTC field on the user portal should left with the long session id that is auto populated. Then the user should enter the their OTC into the phone when prompted.

Status     Log Viewer	Server>Dual Channel 🛽							
Edg Viewer     Server     server	Please select whether dual channel security string messages are delivered preemptively or on demand at the point of authentication.							
• Language • License	On-demand authentication:	No 🔹						
• <u>Jobs</u> • <u>SMTP</u> • Anents	On-Demand Delivery:	Yes •						
O Peers     Single Channel	Allow message request by username:	Yes •						
<u>Dual Channel</u> <u>Third Party Authentication</u> Ovice Channel	Allow alternative usernames:	No •						
Policy	Verification Mode:	Standard - OTC •						
Logging     Transport	Alternative username attributes:							
E Database	Multiple authentications per String:	No 🔻						
Mode     Repository	Confirmation image on message request:	Yes •						
RADIUS	In Bound OTC Rule:	Match -						
Appliance	[server_dualchannel_inboundconfirmkey]:	123						
OATH     Synchronisation Administration	[server_dualchannel_inboundcallgap]:	10						
Reporting	In Bound SMS Timeout (ms):	500						
User Administration     Save Configuration	in bound Ship functure (ins).	Apply Resat						
Administration Guide								
• Logout								

Last configuration for the core is to add the user group i.e pinsafeUsers to the telephony groups. Goto Repository/groups, make sure you check the telephony box on the correct group.

• <u>Status</u> • Log <u>Viswer</u> 8 Server 8 Policy	Repository> Please enter the rep This includes group p	Groups 😻 ository group information t privileges and Active Direct	to be used by the Swiv tory/LDAP definition. Fo	vel server. or XML repo	sitory, pleas	e copy the group	name into th	e definition.			
E Logging				Single	Dual	Telephony	Mobile	Admin	Helpdesk	PINIess	OATH
Transport							Client				
E Database	Name	Othersfellenge			122						
B Mode	Name;	PINsateUsers		(¥)	(¥)	(¥)	(¥)				
Repository     e Servers	Definitions:										Delete
• Types	syedRepo:	PINsafeUsers									
e Attributes	adtest:	CN=1kusers,OU=testing.	DC=test,DC=local								Browse
• svedRepo • adtest	localSimpleLdap:	cn=pinsafe,ou=groups,o	u=system								Browse
ERADIUS	Name:	PINsafeAdministrators		1	<b>X</b>	8	2	1		8	8
Migration	Definitions:										Delete
E Appliance	ever dBaseau	Dibles fo Administrations									
E OATH	syeakepo:	PINSAREAGINITISTRATORS									
E Synchronisation Administration	adtest:										Browse
© Reporting	localSimpleLdap:										Browse
User Administration											
Save Configuration	Name:										
Administration.Guide	Definitions:										
Logout	syedRepo:										
	adtest:										Browse
	localSimpleLdap:										Browse
							Apply	Reset	Group Rights		

That's all we should need to do for the Swivel Core. Next we will deploy the Userportal and use this to test the nexmo voice transport we have just configured.

Setting up the UserPortal to communicate with the core.

Download the user portal to eclipse, open the main/js/ajax.js file and make sure the top line has the serverContext variable set

var serverContext = <u>http://localhost:8080/pinsafe</u>

build and deploy the userportal then open the webpage userportal/telephonylogin now test the login on this page. Use both match and message options to test.