Sentry SSO with PulseSecure

Contents

- 1 Introduction

- a Configuring the PulseSecure VPN
 a Configuring the Sentry Application
 4 Testing authentication to PulseSecure via Swivel AuthControl Sentry

Introduction

This article explains how to integrate a PulseSecure SSL VPN with Sentry.

Configuring the PulseSecure VPN

NOTE: It is assumed that your PulseSecure already has a basic, working configuration.

Log into the PulseSecure administration console. From the menu, select Authentication, then Signing In and Sign-in SAML.

Q Dule	e Secu	re l				Pu	ilse Connect Se
	eJecui	System	Authentication	Administrators	Users	Maintenance	Wizards
Signing In							
Sign-in Policies	Sign-in Pages	Sign-in Notificati	ions Sign-in SAM				
Metadata Provider Ide	entity Provider						
This is configuration of F	Pulse Connect Secure	(SA) SAML Metada	ata provider.				
"Entity Id:			Unique SAML identifier of th	e SA. Uses host name confi	gured at SAML	Settings.	
"Metadata Validity:	365 days		1 - 9999. Specifies the maxi	mum duration for which a pe	er SAML entity	can cache the Connect	Secure metadata fik
Do Not Publish IdP	P in Metadata		Prevents the Connect Secur	e metadata file to be publish	ned at the locat	ion specified by the Entity	y ld.
Download Metadata	a						
Save Metadata Pro	vider Cancel						

Click the link for SAML Settings, at the end of the line for Entity Id.

S Pulse Secure	e _{System}	Authentication	Administrators	Users	Maintenance	Wizards
SAML > Settings						
← Metadata Server Configuration						
Timeout value for metadata fetch request:	300 seconds	1 - 600. Specifies t	he time in seconds to wait f	or response of :	SAML metadata fetch req	uest
Validity of uploaded/downloaded metadata file:	0 days	0 - 9999. Specifies	the time in days after which	h downloaded/u	ploaded metadata file exp	ires. 0 means that Connect Secure doesnot enforc
Host FQDN for SAML:	est.swivelsecure.lo	The FGDN used for	generating URLs for SAML	services		
Alternate Host FQDN for SAML:		The FQDN used for	generating SA's Single Sig	n-On Service UP	L when Pulse(NC) Sessi	on detection is enabled.
Save Changes Cancel Update E	intity Ids					

Enter the public host name of your PulseSecure server under Host FQDN for SAML, and click Save Changes.

Go back to the **Sign-in SAML** page, and ensure that the Entity Id is *https://<pulse_server>/dana-na/auth/saml-endpoint.cgi* - i.e. it should be exactly the same as the Entity ID you put on the Sentry application settings, except for ?*p=sp1*.

Now go to Authentication, Auth. Servers

S	Pulse Secure	System Authenti	Ication Administrators	Users Maintena	nce Wizards	Ρ
Authe	entication Servers					
New:	(Select server type)	New Server	Delete			
10	 records per page 					Sear
۵	Authentication/Authorization Servers		Туре	U	ser Record Synchronization	Logical Auth Server
	Administrators		Local Authentication			
	SentryLore		SAML Server			
	System Local		Local Authentication	e .		

Select SAML Server from the drop-down, then click New Server....

SPI	ulse Secur	C System Authentication	Adr	ninistrators	Users	Maintenance	Wizards	P
Auth Servers > 5	Sentral ore							
SentryLore								
Settings	Users							
Server Name:	SentryLore							
✓ Settings								
*SAML Versi	on:	0 1.1 @ 2.0						
*Connect Ser	cure Entity Id:	/dana-na/auth/saml-endpoint.cgi?p=sp1	Unique S	AML identifier of the	SANL Auth Ser	ver, Uses host name	configured at SAML	Settings
*Configuration	Mode:	🌒 Manual 🔘 Metadata	Uses met	tadala files configure	od al SAML Metz	data for metadata fil	based configuration	
*Identity Provider Entity Id:		168.11.115.8443/sentry/saml20endpoint	Unique S	AML identifier of the	Identity Provider			
Identity Prov	ider Single Sign On Service URL	168.11.115.8443/sentry/sami20endpoint	User is re	edirected to this URL	in destination fi	st scenario.		
User Name	l'emplate:							
		Example: «assertionNameDN uid», uid from X500 The entire assertion name identifier if not specifi «userAttrattr», attr from AttributeStatement attri	ed; Or	ne.				
Allowed Clor	:k Skew (minutes):	5	0 - 9999	minutes				
	Single Logout				aupports sending	and receiving single	logout requests.	
	It Service URL:	192.168.11.115:8443/sentry/singlelogout	Location	at Identity Provider t	o which the sing	le logout request is s	ent.	
Single Logo	rt Response URL:		-					the response is sent to the same location as the
▼ SSO Metho	4							
Artifact Post			41:39 201	6 GMT				
	Upload Certificate Browse	No file chosen Delete						
		Signing Certificate status checking						
	to the certificat	ation in Trusted Client CAs. This applies is configured above as well as the one ith the SAML response.)						
Select Device	Certificate for Signing:	Not Applic	able	Certificate use	d for signing the	Requests initialed by	Connect Secure for	the SAML Auth Server. Select "Not Applicable" it
Select Device	Certificate for Encryption:	Not Applic	able	Certificate use	d by the IdP for	wrapping encryption	keys for the SAML A	uth Server. Select "Not Applicable" if encryption i

Set a name for the server. Ensure that SAML Version is set to 2.0.

Connect Secure Entity Id will be set as the unique entity ID for this server. Make a note of it, as you will be entering it in the Sentry configuration page.

For **Identity Provider Entity Id** and **Identity Provider Single Sign On Service URL**, enter *https://<swivel_server>/sentry/saml20endpoint*. Here, *<swivel_server>* is the public URL of the Swivel sentry server.

Check Support Single Logout, and enter https://<swivel_server>/sentry/singlelogout as the Single Logout Server URL. The Single Logout Response URL is the same, so can be left blank.

NOTE: for the next part, you will need a copy of the metadata from the Swivel Sentry server. If you do not already have one, open your browser to https://<swivel_server>/sentry/metadata/generatedMetadata.xml. When the metadata is displayed in your browser, save it to disk.

♥ SSO Metho	bod		
 Artifact Post 	Response Signing Certificate: Issued To: sentry Issued By: sentry Valid: Sep 29 13:41:39 2016 G Details: I Other Certificate Details	MT - Oct 29 13:41:39 20	16 GMT
	Upload Certificate: Browse No file chosen Delet	te	
	Enable Signing Certificate status	checking	
	(Use's configuration in Trusted Client CAs. Th to the certificate configured above as well as comes along with the SAML response.)		
Select Devic	ce Certificate for Signing:	Not Applicable	Certificate used for signing the Requests initiated by Connect Secure for the SAM, Auth Server, Select "Not Applicate
Select Devic	ce Certificate for Encryption:	Not Applicable	Certificate used by the KIP for wrapping encryption keys for the SAML Auth Server. Select "Not Applicable" if encry
	uested Authn Context Classes to be sent in the AuthReque	st:	
Available: InternetProt	Selected:	*	
S 10 H 50 10			
Kerberos	Remove		
MobileOneF	FactorUnregistered		
MobileTwoF	FactorUnregistered		
Comparison	Method for Authentication Classes:	exact	•
V Service Pr	rovider Metadata Settings		
Metadata Va	alidity: 90 days 1 - 9999. Specifies the time i	days after which metadata	for the SAML Auth Server should be refreshed by the identity Provider. This is used to populate the cache duration field in t
Do Not	Publish Connect Secure MetadataPrevents the Metadata for th	e SAML Auth Server to be po	blished at the location specified by the Connect Secure Entity Id.
Download	d Metadata		
♥ User Reco	ord Synchronization		
En:	able User Record Synchronization		
Log	gical Auth Server Name		
Save Chan	nges		

Ensure that Post is selected as the SSO Method. Click Browse next to Upload Certificate and select the metadata file you downloaded earlier.

Set a valid value for Metadata Validity.

Click Save Changes.

Now Select Users, then User Realms.

💲 Pul	se Secur	e _{System}	Authentication	Administrators	Users	Maintenance	Wizards	Pulse Co
User Realms > s General • Name: Description:	User Realms User Roles Resource Profiles Resource Policies Pulse Secure Client Enterprise Onboarding	User Realm New User	tealm. start on the Role Maj	pping page				
2002/2012/2012 12:00 12:00 12:00 12:00 12:00 12:00 12:00 12:00 12:00 12:00 12:00 12:00 12:00 12:00 12:00 12:00	use for authentication and authe	rization. To create or in	anage servera, see the S	ervers page				
Authentication: User Directory/A Accounting Device Attribute: Additional Authen Enable addition V Dynamic policy et	utribute: 5: mication Server nal authentication server valuation ic policy evaluation	SentryLore None None	•				Specify the server to use for authenticating users. Specify the server to use for authorization. Specify the server to use for Radius accounting. Specify the server to use for device authorization.	
Authentication Role Mapping Save Char						assword restrictions Rule		
* indicates required field								

-

Click **New** to create a new user realm.

General				
General Authentication Policy	Role Mapping			
* Name:	sentryLoreRealm			Label to reference this realm
Description				
	When editing, start on the Role Map	oping page		
♥ Servers				
Specify the servers to use for authentication and a	udhorization. To create or manage servers, see the S	ervers page		
Authentication:	SentryLore			Specify the server to use for authenticating users.
User Directory/Attribute:	None			Specify the server to use for authorization
Accounting:	None			Specify the server to use for Radus accounting
Device Attributes:	None			Specify the server to use for device authorization.
V Additional Authentication Server				
Enable additional authentication server	1			
Dynamic policy evaluation				
Enable dynamic policy evaluation				
♥ Session Migration				
♥ Other Settings				
Authentication Policy.			Password restrictions	
Role Mapping			1 Rule	
Save Changes				
* indicates required field				

Add a name, then under Authentication, select your new authentication server. Click Save Changes.

Now under **Role Mapping**, select the role(s) that users will be assigned. For example, in the following role mapping, all users are assigned to the Role **Users**.

User Realms > :	sentyLoreHealm > Hore Mapping			
Role Mappin	9			
General	Authentication Policy Role Mapping			
Specify how to	assign roles to users when they sign in. Users that are not assigned a	role will not be able to sign in.		
New Rule	Duplicate Delete			
•	When users meet these conditions		assign these roles	
E 1,	usemame is "**	\rightarrow	Users	
	n one role is assigned to a user: ngs for all assigned roles			
	select from among assigned roles			
	select the sets of merged roles assigned by each rule			
	o not meet any of the above rules will not be able to sign into this realm			
800,900,900,900,900,900,900 800,900,900,900,900,900,900,900,900,900,				

Finally, go to Authentication, Signing In, Sign-in Policies. Click New URL.... Enter the Sign-in URL, then select User picks from a list of authentication realms and add the user realm created above. Click Save Changes.

Configuring the Sentry Application

Log into the Sentry administration console. Select Applications. Then Click Add Application and select SAML - PulseSecure

iles	SAML Applic	SAML Application					
plications							
thentication Methods							
w IdP Metadata	Note: The	Endpoint URL is used only if the ACS (Assertion Consumer Service) is not supplied in the					
Ha		curity Assertion Markup Language) request.					
ers Active Sessions							
er History	Name	PulseSecure					
g Viewer							
neral Configuration							
plication Images	Image	PulseSecure.png V SPulse Secure					
	Points	0					
		-					
	Portal URL	https://yourdomain/yourcontext					
	Endpoint URL	https://yourdomain/dana-na/auth/saml-consumer.cgi					
	Entity ID	https://yourdomain/dana-na/auth/saml-endpoint.cgi?p=sp1					
	Federated Id	email					

NOTE: for all the following, replace <pulse_server> with the public host name for your Pulse server.

Under Portal URL, enter the URL for the PulseSecure portal that will be authenticated using Sentry, for example https://<pulse_server>/saml.

Under Endpoint URL, enter https://<pulse_server>/dana-na/auth/saml-consumer.cgi.

Under Entity ID, enter the unique Entity ID you recorded from the PulseSecure authentication server.

Under Federated Id, enter email.

Testing authentication to PulseSecure via Swivel AuthControl Sentry


This should be the final step after all previous elements have been configured.

Visit your AuthControl Sentry Page with your public DNS entry of your Swivel AuthControl Sentry server, e.g. https://mycompanysentrydomain/sentry/startPage On a Start Page you will be able to see a new PulseSecure Icon on which you can click and proceed with authentication (as you would by going straight to the PulseSecure page)




When you visit this URL you will notice that the domain should redirect to the identity provider login URL that you setup, once you have submitted your username. You should be presented with the page of the Authentication Method which can score enough points to match the points required by the PulseSecure Application definition.

In this login example we are using the email as a username



After we enter the username we are prompted with another authentication method (in this example we use turing)



After we enter our authentication credentials we successfully will see the PulseSecure that we tried to access.