

Settings

Settings

You can generally access the USAM Admin console using the same username and PIN from a Admin Account on the Swivel Core server that the USAM is working with. However you may need to change some settings first if you are running a non standard installation.

These settings are under `\home\swivel\swivel\authentication-manager` in a file called `settings.properties`

The first section dictates how the USAM should communicate with the Core Server. It is recommended you change the default secret before putting into production

```
pinsafessl=false
pinsafeserver=localhost
pinsafecontext=pinsafe
pinsafesecret=secret
pinsafeport=8181
```

The next section dictates how the USAM should retrieve images from the core

```
imagesssl=false
imageserver=localhost
imagecontext=proxy
imageport=8443
selfsigned=true
```

This entry determines which Swivel Core server group a user must be a member of in order to access the USAM Admin console

```
administrationGroup=PINSafeAdministrators
```

The following section defines the format of the certificates and keys used by the platform and where they are stored

```
certificateIssuer=SAML_SP
encryptionType=DSA
publicKeyFileName=/keys/dsapubkey.der
privateKeyFileName=/keys/dsaprivkey.der
certificateFileName=/keys/dsacert.pem
```

Time Polling is used by the OneTouch Authentication method to determine how long the long in page will wait for the user's response.

```
timeoutPolling=60000
```

When a user authenticates to a service the platform needs to map the presented ID to a user attribute associated with the user on the Swivel Core Server. This is usually their email address as this is the attribute generally used as a username by cloud service providers.

```
federatedIDAttribute=email
```

This is the URL of the home page for the authentication manager

```
applicationRootURL=http://127.0.0.1:8080/swivelauthenticationmanager
```

This is the url that will be used for GeoIP look ups. It is possible to host your own GeoIP server in which case this value would need to be changed accordingly

```
freegeoipurl=https://freegeoip.net/xml/
```

The tomcat service will need restarting for changes to take affect.