

# SCText How To Guide

## Contents

- 1 Overview
- 2 Prerequisites
- 3 How to Guide
  - ◆ 3.1 Enabling SCText
  - ◆ 3.2 Making SCText requests by username
  - ◆ 3.3 Making SCText requests by SessionID
- 4 Testing
- 5 Known Issues
- 6 Troubleshooting

## Overview

The SCText servlet allows security strings to be requested by using a text string. It is disabled by default and if required must be explicitly enabled.

## Prerequisites

PINsafe 3.x

## How to Guide

### Enabling SCText

To enable the SCText servlet, edit web.xml on the PINsafe web application (under <Tomcat\_root>\pinsafe\WEB-INF). Check if the following lines exists:

```
<servlet>
  <servlet-name>SCText</servlet-name>
  <servlet-class>com.swiveltechnologies.pinsafe.server.session.SCText</servlet-class>
</servlet>
```

Insert them if they do not, next to the other servlet definitions. The other section will almost certainly be missing:

```
<servlet-mapping>
  <servlet-name>SCText</servlet-name>
  <url-pattern>/SCText</url-pattern>
</servlet-mapping>
```

Insert this section next to the other <servlet-mapping> entries.

Save web.xml and restart Tomcat.

### Making SCText requests by username

You should now be able to make requests as follows to receive text security strings:

For a Software install:

http://<pinsafe>:8080/pinsafe/SCText?username=test

For an Appliance

https://<pinsafe>:8080/pinsafe/SCText?username=test

Example output:

1234567890

4507826913

### Making SCText requests by SessionID

If "Allow session start by username" is disabled, you need to execute a session start request, retrieve the session ID and use the following format:

For a Software install:

http://<pinsafe>:8080/pinsafe/SCText?sessionid=<sessionid>

For an Appliance

https://<pinsafe>:8080/pinsafe/SCText?sessionid=<sessionid>

**Testing**

**Known Issues**

**Troubleshooting**