# Sentry SSO with PulseSecure

## Contents

- 1 Introduction

- a Configuring the PulseSecure VPN
  a Configuring the Sentry Application
  4 Testing authentication to PulseSecure via Swivel AuthControl Sentry

### Introduction

This article explains how to integrate a PulseSecure SSL VPN with Sentry.

# Configuring the PulseSecure VPN

NOTE: It is assumed that your PulseSecure already has a basic, working configuration.

Log into the PulseSecure administration console. From the menu, select Authentication, then Signing In and Sign-in SAML.

Q Dule	Secu	ro				Pu	lse Connect Se
	esecu	System	Authentication	Administrators	Users	Maintenance	Wizards
Signing In							
Sign-in Policies	Sign-in Pages	Sign-in Notificati	ions Sign-in SAM	<b>-</b>			
Metadata Provider Ide	entity Provider						
This is configuration of F	Pulse Connect Secure	(SA) SAML Metada	ata provider.				
"Entity Id:	https://puisetest.s	swivelsecure.local/da	Unique SAML identifier of th	e SA. Uses host name confi	gured at SAML	Settings.	
"Metadata Validity:	365 days		1 - 9999. Specifies the maxi	mum duration for which a pe	er SAML entity	can cache the Connect	Secure metadata file
Do Not Publish IdP	in Metadata		Prevents the Connect Secur	e metadata file to be publish	ned at the locat	ion specified by the Entity	y ld.
Download Metadata	•						
Save Metadata Pro	vider Cancel						

Click the link for SAML Settings, at the end of the line for Entity Id.

S Pulse Secure	e <sub>System</sub>	Authentication	Administrators	Users	Maintenance	Wizards
SAML > Settings						
← Metadata Server Configuration						
Timeout value for metadata fetch request:	300 seconds	1 - 600. Specifies th	te time in seconds to wait f	or response of :	SAML metadata fetch req	uest
Validity of uploaded/downloaded metadata file:	0 days	0 - 9999. Specifies	the time in days after which	n downloaded/u	oloaded metadata file exp	ires. 0 means that Connect Secure doesnot enforc
Host FQDN for SAML:	est.swivelsecure.loc	the FGDN used for	generating URLs for SAML	services		
Alternate Host FQDN for SAML:		The FQDN used for	generating SA's Single Sig	n-On Service UP	IL when Pulse(NC) Sessi	on detection is enabled.
Save Changes Cancel Update E	ntity Ids					

Enter the public host name of your PulseSecure server under Host FQDN for SAML, and click Save Changes.

Go back to the **Sign-in SAML** page, and ensure that the Entity Id is *https://<pulse\_server>/dana-na/auth/saml-endpoint.cgi* - i.e. it should be exactly the same as the Entity ID you put on the Sentry application settings, except for ?*p=sp1*.

#### Now go to Authentication, Auth. Servers

S	<b>Pulse</b> Secure	System Authenticatio	n Administrators User	rs Maintenance Wizards	Ρ
Authe	entication Servers				
New:	(Select server type)	New Server Delete	and a		
10	records per page				Sear
۵	Authentication/Authorization Servers		Туре	User Record Synchronization	Logical Auth Server
	Administrators		Local Authentication		
	SentryLore		SAML Server		
	System Local		Local Authentication		

Select SAML Server from the drop-down, then click New Server....

S Pulse S	ecure	System Authent	ication A	dministrators	Users	Maintenance	Wizards	P
Auth Servers > SentryLore								
SentryLore								
Settings Users								
Server Name SentryLore								
♥ Settings								
*SAML Version:		1.1 @ 2.0						
*Connect Secure Entity Id:	ſ	/dana-na/auth/saml-endpoint.cp	pi?p=sp1 Unique	sAML identifier of th	ie SAML Auth Ser	ver. Uses host name i	configured at SAML Se	ttings
*Configuration Mode:	1	🖲 Manual 💿 Metadata	Uses	netadala files configu	red at SAML Meta	data for metadata file	based configuration.	
"Identity Provider Entity Id:	ſ	168.11.115.8443/sentry/sami20	endpoint Unique	e SAML identifier of th	ie Identity Provider			
Identity Provider Single Sign O	n Service URL	168.11.115.8443/sentry/sami20	endpoint User a	redirected to this UR	8. in destination fit	st scenario.		
User Name Template:	ſ							
	E	ample: «assertionNameDN.uid», uid e entire assertion name identifier if r serialitr attra, attr from AttracteState	from X509Subject/ lot specified; Or	lame.				
Allowed Clock Skew (minutes)	- E	5	0 - 99	99 minutes				
Support Single Logout	a 6 5		If chee	skeð, Connect Secure	aupports sending	and receiving single	lögöut requests.	
*Single Logout Service URL:	ſ	192.168.11.115:8443/sentry/sing	pelogout Locati	on at identity Provider	to which the sing	ie logout request is se	ent.	
Single Logout Response URL:	ſ		Locati	om at klentity Provider	to which the sing	e logout response is	sent. If not specified th	e response is sent to the same location as the
▼ SSO Method								
Artifact Response Signin     Post	g Certificate: Issued To: se Issued By: se Valid: Se Details: ►O	ntry ntry ip 29 13:41:39 2016 GMT - Oc her Certificate Details	t 29 13:41:39 2	016 GMT				
Upload Certificat	Browse	No file chosen Delete						
	(Uses configurati to the certificate of comes along with	on in Trusted Clent CAs. This applet on figured above as well as the one the SAML response.)						
Select Device Certificate for Sig	ning:	N	ot Applicable	Certificate us	red for signing the	Requests initiated by	Connect Secure for th	e SAML Auth Server. Select "Not Applicable" if
		100						

Set a name for the server. Ensure that SAML Version is set to 2.0.

Connect Secure Entity Id will be set as the unique entity ID for this server. Make a note of it, as you will be entering it in the Sentry configuration page.

For Identity Provider Entity Id and Identity Provider Single Sign On Service URL, enter https://<swivel\_server>/sentry/saml20endpoint. Here, <swivel\_server> is the public URL of the Swivel sentry server.

Check Support Single Logout, and enter https://<swivel\_server>/sentry/singlelogout as the Single Logout Server URL. The Single Logout Response URL is the same, so can be left blank.

NOTE: for the next part, you will need a copy of the metadata from the Swivel Sentry server. If you do not already have one, open your browser to https://<swivel\_server>/sentry/metadata/generatedMetadata.xml. When the metadata is displayed in your browser, save it to disk.

♥ SSO Metho	bod		
<ul> <li>Artifact</li> <li>Post</li> </ul>	Response Signing Certificate: Issued To: sentry Issued By: sentry Valid: Sep 29 13:41:39 2016 G Details: I Other Certificate Details	MT - Oct 29 13:41:39 20	16 GMT
	Upload Certificate: Browse No file chosen Delet	te	
	Enable Signing Certificate status	checking	
	(Use's configuration in Trusted Client CAs. Th to the certificate configured above as well as comes along with the SAML response.)	is applies sithe one	
Select Devic	ce Certificate for Signing:	Not Applicable	Certificate used for signing the Requests initiated by Connect Secure for the SAM, Auth Server, Select "Not Applica
Select Devic	ce Certificate for Encryption:	Not Applicable	Certificate used by the KIP for wrapping encryption keys for the SAML Auth Server. Select "Not Applicable" if encry
Select Requ	uested Authn Context Classes to be sent in the AuthReque	st:	
Available:	Selected:	*	
InternetProt	tocol E (none)		
Kerberos	Remove		
MobileOneF	FactorUnregistered		
MobileTwoF	FactorUnregistered		
Comparison	Method for Authentication Classes:	exact	•
V Service Pr	rovider Metadata Settings		
Metadata Va	alidity: 90 days 1 - 9999. Specifies the time i	days after which metadata	for the SAML Auth Server should be refreshed by the identity Provider. This is used to populate the cache duration field in t
Do Not	Publish Connect Secure MetadataPrevents the Metadata for th	e SAML Auth Server to be po	blished at the location specified by the Connect Secure Entity Id.
Download	d Metadata		
♥ User Reco	ord Synchronization		
En:	able User Record Synchronization		
Log	gical Auth Server Name		
Save Chan	nges		

Ensure that Post is selected as the SSO Method. Click Browse next to Upload Certificate and select the metadata file you downloaded earlier.

Set a valid value for Metadata Validity.

Click Save Changes.

Now Select Users, then User Realms.

S Puls	e Secure	System	Authentication	Administrators	Users	Maintenance	Wizards	Pulse Col
User Realms > 1 General General Name: Description: E	Jser Realms Jser Roles Resource Profiles Resource Policies Pulse Secure Client Enterprise Onboarding	User Realin New User	ns kealm start on the Role Maj	oping page				
Specify the servers to use	e for authentication and authors	zation. To create or n	ianape servera, see the S	ervers page.				
Authentication: User Directory/Attri Accounting: Device Attributes: Additional Authentic Enable additional User Dynamic policy evaluation	ibute: ation Server authentication server sation	SentryLore None None					Specify the server to use for authenticating users. Specify the server to use for authorization. Specify the server to use for Radius accounting. Specify the server to use for device authorization.	
Enable dynamic (	policy evaluation							
<ul> <li>Session migration</li> <li>Other Settings</li> </ul>								
Authentication Pol Role Mapping	iicy:				P 1	assword restrictions Rule		
* indicates required field								

-

Click **New** to create a new user realm.

General			
General Authentication Policy	Role Mapping		
* Name:	sentryLoreRealm		Label to reference this ream
Description:			
	When editing, start on the Role Map	ping page	
✓ Servers			
Specify the servers to use for authentication and	authorization. To create or manage servers, see the S4	ervers page	
Authentication:	SentryLore •		Specify the server to use for authenticating users.
User Directory/Attribute:	None		Specify the server to use for authorization
Accounting	None		Specify the server to use for Radius accounting
Device Attributes:	None		Specify the server to use for device authorization.
V Additional Authentication Server			
Enable additional authentication serve	er		
· Dynamic policy evaluation			
Enable dynamic policy evaluation			
Session Migration			
♥ Other Settings			
Authentication Policy: Role Mapping:		Password 1 Rule	restrictions
Save Changes			
* indicates required field			

Add a name, then under Authentication, select your new authentication server. Click Save Changes.

Now under **Role Mapping**, select the role(s) that users will be assigned. For example, in the following role mapping, all users are assigned to the Role **Users**.

Role Mapping	
General Authentication Policy Role Mapping	
Specify how to assign roles to users when they sign in. Users that are not assigned a role will not be able to sign in.	
New Rule Duplicate Delete	
When users meet these conditions     assign these roles	
□ 1. usemame is <sup></sup> Users	
When more than one role is assigned to a user	
Werge seconds for an assigned roles	
User must select non among assigned roles     Iser must select the sets of memod inles sestimed by each nile	
D oon uner saar na oste e under oos stedne ok seen ne	
Note: Users that do not meet any of the above rules will not be able to sign into this ream.	

Finally, go to Authentication, Signing In, Sign-in Policies. Click New URL.... Enter the Sign-in URL, then select User picks from a list of authentication realms and add the user realm created above. Click Save Changes.

# **Configuring the Sentry Application**

Log into the Sentry administration console. Select Applications. Then Click Add Application and select SAML - PulseSecure

	SAML Application					
plications						
thentication Methods						
w IdP Metadata	Note: The	Endpoint URL is used only if the ACS (Assertion Consumer Service) is not supplied in the				
Ha.	SAML (Se	curity Assertion Markup Language) request.				
ers Active Sessions						
er History	Name	PulseSecure				
g Viewer						
meral Configuration						
plication Images	Image	PulseSecure.png V SPulseSecure				
	Points	0				
	Portal URL	https://yourdomain/yourcontext				
	Endpoint URL	https://yourdomain/dana-na/auth/saml-consumer.cgi				
	Entity ID	https://yourdomain/dana-na/auth/saml-endpoint.cgi?p=sp1				
	1.000 m 4 0 m					
	Federated Id	email				

NOTE: for all the following, replace <pulse\_server> with the public host name for your Pulse server.

Under Portal URL, enter the URL for the PulseSecure portal that will be authenticated using Sentry, for example https://<pulse\_server>/saml.

Under Endpoint URL, enter https://<pulse\_server>/dana-na/auth/saml-consumer.cgi.

Under Entity ID, enter the unique Entity ID you recorded from the PulseSecure authentication server.

Under Federated Id, enter email.

### Testing authentication to PulseSecure via Swivel AuthControl Sentry

This should be the final step after all previous elements have been configured.

Visit your AuthControl Sentry Page with your public DNS entry of your Swivel AuthControl Sentry server, e.g. https://mycompanysentrydomain/sentry/startPage On a Start Page you will be able to see a new PulseSecure Icon on which you can click and proceed with authentication (as you would by going straight to the PulseSecure page)



When you visit this URL you will notice that the domain should redirect to the identity provider login URL that you setup, once you have submitted your username. You should be presented with the page of the Authentication Method which can score enough points to match the points required by the PulseSecure Application definition.

In this login example we are using the email as a username



After we enter the username we are prompted with another authentication method (in this example we use turing)



After we enter our authentication credentials we successfully will see the PulseSecure that we tried to access.