

Joomla 1.6 PINsafe Module

Contents

- [1 Introduction](#)
- [2 Prerequisites](#)
- [3 Modifying the Module](#)
 - ◆ [3.1 Add Modified files to the Archive](#)
- [4 Uploading the Module](#)
- [5 Configuring the Module](#)

Introduction

This document describes how to upload and publish the PINsafe Joomla Module. For further information see [Joomla 1.6 Integration](#)

Prerequisites

Joomla 1.6

PINsafe 3.x

[Joomla 1.6 Integration](#)

[PINsafe Module](#)

Modifying the Module

Edit the mod_pinsafe.php file

Look for and change the line containing the PINsafe server IP address, this will need to be an address accessible to the user wishing to authenticate and may be a NAT and PAT.

```
pinsafeUrl = "http://192.168.22.1:8080/pinsafe/";
```

for a Swivel virtual or hardware appliance use:

```
pinsafeUrl = "http://PINsafe_IP_or_Hostname:8443/proxy/";
```

For a software only install see [Software Only Installation](#)

Additional modifications can be made to prevent buttons that are not required from being displayed

Remove each line that is not required:

```
<input type="button" value="TURing" onclick="showTuring();">
```

```
<input type="button" value="Index" onclick="showIndex();">
```

```
<input type="button" value="Message" onclick="showMessage();">
```

Save the file when complete

Add Modified files to the Archive

Add the mod_pinsafe.php to the mod_pinsafe.zip archive file

Uploading the Module

On the Joomla Administration Console, select Extensions then Extension Manager. select the mod_pinsafe.zip archive file, then click upload

Administration

Site

Users

Menus

Content

Components

Extensions

Help



Extension Manager: Install

Install

Update

Manage

Discover

W



Extension Manager



Module Manager



Plug-in Manager



Template Manager



Language Manager

Upload Package File

Package File

Browse...

Upload & Install

Install from Directory

Install Directory

/tmp

Install

Install from URL

Install URL

http://

Install

A message should indicate success: "Installing module was successful."

Configuring the Module

Follow the instructions for configuring a configuring a custom module [Joomla_1.6_Integration#Configuring_the_PINsafe_login_module](#). The cache option will not be present.