

Sentry Core V4 Menu Reference

Contents

- 1 Introduction
- 2 Logging In
- 3 Swivel Web Console Main Menu
 - ◆ 3.1 Status Screen
 - ◆ 3.2 Save Configuration
 - ◆ 3.3 Upload Email Images
 - ◆ 3.4 Administration Guide

Introduction

This article is a complete reference to the Swivel Core Administration Web Console. This page lists all the top-level menus, and each menu has its own page, referenced from this page, with the exception of a few that can be summarized within this page.


Logging In

To log into the Swivel Web Console, enter the following URL into a web browser:

`https://<swivel_server>:8080/sentry`

Here, <swivel_server> is the IP address or host name of the Swivel appliance.

You should be presented with the following login screen:



Enter the username of an administrator. The shipped application comes with a user named **admin**. Click on **Start Session** and a TURING image will be displayed.

You now need to enter your one-time code based on the TURING image shown. The default PIN for the **admin** user is **1234**, so enter the first 4 digits of the TURING string - in this case **5034**.


If this is the first time you have run the web console, you will be presented with the End-User Licence Agreement.

BETWEEN S
person or e
(as defined
ACTIVATION
activation k
software se
software se
LICENSE.
Service Off
Customer a
(i) to use th
the usage l
(ii) not to s
be conclusi
(iii) not to
decode the
any such ac
(iv) not to
Offering, ex
associated
by Supplier
(v) to pay
are calculat
the level of
access repo
and investig
(vi) that th
number of
Supplier or
applicable p
activation k
(vii) not to
the Service
permitted h
(viii) not to

Do Not Ac

You should read this, and assuming you accept it, click on "Accept EULA" to continue.

You will now be presented with the Status page.

swivelsecure

Status

Log Viewer

▸ Server

▸ Policy

▸ Logging

▸ Messaging

▸ Database

▸ Mode

▸ Repository

▸ RADIUS

▸ Migration

▸ Appliance

▸ OATH

▸ Config Sync

▸ Reporting

User Administration

Save Configuration

Upload Email Images

Administration Guide

Logout

Sentry Status ?

Server

Active databaseAppliance D

ModeSynchroniz

Sentry RADIUS EnabledYes

Server IP address10.130.0.95

Server hostname10.130.0.95

Repository server nameLocal

Repository server ID1

Logged in asswivel

Configuration version4.1.0.2

Data Storage Root/home/swiv

End User Licence AgreementView

Transport

Transport Queue: SMTP0 messages

Transport Queue: AQL0 messages

The main menu is shown down the left side of the page. The following chapter summarises the menu items.

Swivel Web Console Main Menu

Status	Shows the status page
Log Viewer	Shows the logs
Server	Swivel Server Configuration
Policy	Authentication Policy Configuration
Logging	Logging Configuration
Messaging	Mail and Mobile phone messaging configuration
Database	Database configuration
Mode	Mode configuration

Repository	User repository configuration
RADIUS	RADIUS authentication configuration
Migration	Migrate database
Appliance	Appliance synchronization settings
OATH	OATH token management
Config Sync	configuration synchronization settings
Reporting	Data reporting
User Administration	User Administration
Save Configuration	Save the configuration
Upload Email Images	Upload images for use in emails
Administration Guide	Show the administration guide
Logout	Log out from the administration console

Status Screen

As seen above, this shows a summary of the system status, including the total number of users, numbers of users in particular states, licence information etc.

Save Configuration

This option downloads the current server configuration as an XML file, which can be used to restore the configuration in case of data loss. Note that the Swivel appliance takes daily backups, which includes the configuration.








Upload Email Images

This option shows a list of images that can be used in emails. It also allows you to upload new images.

Email Images ?

Images for use in emails can be viewed on this page, and uploaded using the form below.

File for upload:

Image	Image Filename	Image URL	Action
	Activate.jpg	%BASE_URL/proxy/images/email/Activate.jpg	<input type="button" value="Delete"/>
	Activate.png	%BASE_URL/proxy/images/email/Activate.png	<input type="button" value="Delete"/>
	Android.png	%BASE_URL/proxy/images/email/Android.png	<input type="button" value="Delete"/>
	Apple.png	%BASE_URL/proxy/images/email/Apple.png	<input type="button" value="Delete"/>
	Blackberry.jpg	%BASE_URL/proxy/images/email/Blackberry.jpg	<input type="button" value="Delete"/>
	Factors3sm.jpg	%BASE_URL/proxy/images/email/Factors3sm.jpg	<input type="button" value="Delete"/>
			<input type="button" value="Delete"/>

Administration Guide

This displays a guide to administering the Swivel server.