

Console Access How to guide

Contents

- [1 Overview](#)
- [2 Prerequisites](#)
- [3 Console Access Methods](#)
 - ◆ [3.1 Virtual Machine \(VM\) Console](#)
 - ◆ [3.2 Secure Shell \(SSH\)](#)
 - ◆ [3.3 WinSCP](#)
 - ◆ [3.4 Hardware Appliance Console \(KVM\)](#)
 - ◆ [3.5 Hardware Appliance Dell Remote Access Card \(DRAC\)](#)
- [4 Issuing Commands through the command line](#)
 - ◆ [4.1 Using Ascii codes at the command line](#)
 - ◆ [4.2 Commonly used Ascii codes](#)
- [5 Known Issues](#)
- [6 Troubleshooting](#)

Overview

Swivel appliances are configured using the Command Management Interface (CMI) through the console, this document outlines how to access the console. For access to the Command Line see [Command Line Access How to guide](#).

Prerequisites

Swivel appliance 2.x

Console Access Methods

Console access to Swivel appliances is available in the following ways:

Virtual Machine (VM) Console

Virtual machines provide console access using the **admin** user through the Virtual Machine management tools.

Secure Shell (SSH)

SSH access can be made using the **admin** user to the appliance IP address on port 22. See [PuTTY How To Guide](#) for more information.

WinSCP

For uploading and Downloading files using the **admin** user , see [WinSCP How To Guide](#).

Hardware Appliance Console (KVM)

Hardware appliances support the use of a Keyboard, Video and Mouse for console access using the **admin** user .

Hardware Appliance Dell Remote Access Card (DRAC)

Hardware appliances support where present the out of band Dell Remote Access Cards, see [DRAC Card How To Guide](#)

Issuing Commands through the command line

Different keyboard mappings may make it difficult to enter some commands, this can commonly occur when a VPN or remote desktop sharing is used to further access the command line through the console. The following describes the use of Ascii codes to obtain the correct character.

Using Ascii codes at the command line

When using Ascii codes press the Alt key together with the number keys of the Ascii code. This is done using the numeric keypad (laptops may require the Fn key and the Alt key to be used).

e.g. FnALT124

Commonly used Ascii codes

! 33

' 39

- 45

/ 47

\ 92

| 124

Known Issues

Troubleshooting