Swivel Core V4 OATH Menu

Contents

- 1 OATH Policies
 2 OATH Tokens
 3 OATH Assign User
 4 Sync Token With Server
 5 New OATH Token
 6 Import OATH Tokens to database
 7 OATH Users
 8 OATH Assign Token

OATH Policies



🔀 swivelsecure

Status

- Log Viewer
- Server
- Policy
- Logging
- Messaging
- Database
- Mode
- Repository
- RADIUS
- Migration
- Appliance
- OATH
 - > OATH Policies
 - > OATH Tokens
- > OATH Users
- Config Sync
- Reporting
- User Administration
- Save Configuration
- Upload Email Images
- Administration Guide
- Logout

OATH / OATH Policies

Settings for OATH Tokens, note HOTP means event-based, 7

Token Type:	
OTP Length:	e
Error Window (Events):	5
Sync Windows (Events):	1
Append PIN (if user has one) after OTP:	
OCRA Suite:	(



This screen allows you to configure token policies.

- Token type: Swivel supports two variations on Tokens. TOTP (that are time-based) and HOTP (that are event-based). A single installation OTP Length: This define the length of OTP that the tokens are created or imported this setting determines what kind of tokens they are.
 OTP Length: This define the length of OTP that the tokens support. Tokens supplied by Swivel will have six digits. If you choose to deploy different tokens, this setting will need to match the length of OTP displayed by the tokens.
 Error Window (Events): For event based tokens, users pressing the token button may cause the token to become out of sync with the Circle of the token to become out of the token to b
- server. Similarly for time-based tokens clock-drift may have the same effect. The error window allows the server to make allowances for this and will not only check the OTP for the expected event or time but will also check within an error window. So if the server is expecting the user to submit the OTP from event number 25 of their token but they submit the OTP for event number 27 if the Error Window is 2 or more this

would be treated as a successful authentication and the token would be brought back into sync. For time based tokens each event is equivalent to 1 minute. So an error window of 2 would allow a clock drift of plus or minus one minute.

- Sync Window (Events): The Sync window allows tokens to be brought back into sync with the server. For example if the server is expecting
 the user to submit the OTP related to event 27 but the user submits the OTP associated with event 30. As this is outside the error window this
 would lead to a failed authentication. However if this was within the limit of the Sync Window the token would be resynced to the new value
 and therefore the next authentication attempt should succeed
- and therefore the next authentication attempt should succeed.
 Append PIN (if user has one) after OTP: If required you can require the user to append their PIN after their token OTP. This mitigates the risks of token loss.
- OCRA Suite: Swivel Supports OCRA (Oath Challenge Response Algorithm). This is where a challenge is used along with the token seed and event number (or time) the create a OTP. Swivel can supply OCRA tokens that confirm to. By default is set to OCRA-1:HOTP-SHA1-8:QN08-T1M. However the platform can support other OCRA suites.

OATH Tokens



🗟 swivelsecure

C

Status

- Log Viewer
- Server
- Policy
- Logging
- Messaging
- Database
- Mode
- Repository
- RADIUS
- Migration
- Appliance
- OATH
 - > OATH Policies
 - > OATH Tokens
 - > OATH Users
- Config Sync
- Reporting
- User Administration
- Save Configuration
- Upload Email Images
- Administration Guide
- Logout

OATH /	OATH Toke	ens 😧	
Total numb	er of tokens:	0	
Tokens per page:		50	
Search by s	erial ID:		
Search by u	isername:		
Search	New Token	Import	

Serial ID	Туре	Imported on	Allocated User	Allocated on

- This screen allows you to assign users to tokens that have been synced into the Swivel database. Search functionality enables you to filter the list by username or token serial ID. You can resynchronise the token count for those tokens and you can insert new tokens.
 - Search: Allows you to filter the tokens by serial ID and/or username.
 - Tokens per page: Allows you to specify the number of tokens displayed per page.
 - Search by serial ID: Returns the tokens which contain the specified value in the serial ID.
 - Search by username: Returns the tokens which contain the specified value in the username of the user assigned to the token.
 New Token: Allows you to create a new token. When you click the button, a new screen appears that presents a form to introduce the data
 - needed to create a new token.
 - Import: Allows you to import tokens through a file. When you click the button, a new screen appears that allows you select the file to import.
 Assign User: This button appears when the token has a user allocated. When you click the button, a new screen appears that presents a list of unallocated users that are members of a group with the OATH privilege for you to select from.

- Un-assign: When a token has a user allocated, this button appears in the corresponding row. Also allows you to un-assign the current token's user.
- Re-sync: Allows you to resynchronise the current token. When you click the button, a new screen appears that presents two 'One Time Password' fields. Enter a One Time Password from the token in the first field, retrieve the next One Time Password from the Token and enter this into the second field. Press OK to re-sync the token.

a 1170

• **Delete**: Allows you to delete the current token.

OATH Assign User



swivelsecure

- Status
- Log Viewer
- Server
- Policy

- E OATH
 - OATH Policies
 - OATH Tokens
 - OATH Users
- Config Sync
- User Administration
- <u>Save Configuration</u>
- <u>Upload Email Images</u>
- Administration Guide
- Logout

OATH Assign user 🛽

100000100070

Jsers per pag		50	
Search by use	rname :		
		Search	
Username		_	
admin	Select]	
TEST2	Select]	
test3	Select]	
test4	Select]	
test5	Select]	
test6	Select]	
test7	Select]	
test8	Select]	
test9	Select]	
iganulevics	Select]	
helpdesk	Select]	

This screen shows users that are members of a group with the OATH privilege which do not currently have a token assigned. It allows you to assign a user to a token and search users by username.

- Search: Allows you to filter the users by username.
- Users per page: Allows you to specify the number of users displayed per page.
- Search by username: Returns the usernames containing the specified value.
- Select: Assigns the user to the current token and returns to the OATH Tokens screen.

Sync Token With Server



<u>Status</u>	Sync Token With Server @			
Log Viewer	Sync Token W			
Server	Serial Number:	1000302109373		
Policy		1000002105575		
Logging	Username:			
Messaging	One Time Password 1:			
Database	One Time Password 2:			
Mode				
Repository		OK Cance		
RADIUS				
Migration				
Appliance				
 OATH OATH Policies OATH Tokens OATH Users 				
Config Sync				
Reporting				
<u>User Administration</u>				
<u>Save Configuration</u>				
<u>Upload Email Images</u>				
<u>Administration Guide</u>				
• Logout				

Т

This screen presents two 'One Time Password' fields. Enter a One Time Password from the token in the first field, retrieve the next One Time Password from the Token and enter this into the second field. Press OK to re-sync the token.

Serial Number: Specify the serial number of the token to resynchronise.
Username: Specify the username of the allocated user. It will be empty if the token doesn't have a allocated user.
One Time Password 1: Allows you to specify the first One Time Password.
One Time Password 2: Allows you to specify the second One Time Password.

New OATH Token



-		
-	tа	-
-	LCI	

- Log Viewer
- Server
- Policy
- Logging
- Messaging
- Database
- Mode
- Repository
- RADIUS
- Migration
- Appliance
- OATH
 - > OATH Policies
 - > OATH Tokens
 - > OATH Users
- Config Sync
- Reporting
- User Administration
- Save Configuration
- **Upload Email Images**
- Administration Guide
- Logout

OATH / OATH Tokens / New OATH To

Serial ID:			1	
Seed:				
Event Count:			0	
Finished	Save	Cancel		

This screen allows you to create a new Token.

- Serial ID: Allows you to specify the Serial ID.
 Seed: Allows you to specify the seed.
 Event Count: Allows you to specify the event count.

Import OATH Tokens to database



🔁 swivelsecure

Status

- Log Viewer
- Server
- Policy
- Logging
- Messaging
- Database
- Mode
- Repository
- RADIUS
- Migration
- Appliance
- OATH
 - > OATH Policies
 - > OATH Tokens
 - > OATH Users
- Config Sync
- Reporting
- User Administration
- Save Configuration
- **Upload Email Images**
- Administration Guide
- Logout

OATH / OATH Tokens / Import OATH

Please enter the information required below, then click Impo

File Type:	CSV
Token Type:	TOTP (Time Based)
File to Import:	Escolher ficheiro
	File is zipped
	Delete imported to
Import Cancel	

This screen allows you to import tokens from a file.

- File Type: Allows you to specify the file type.
 File is zipped: Allows you to specify if the file is zipped.
 Delete imported tokens: If this option is set to "Yes" when importing a list of tokens, then instead of adding any new tokens it finds from the tokens. Browse: Allows you to select the file that contains the tokens.
 Import: Allows you to import the tokens from the specified file.

- Cancel: Allows you to close the current screen and returns to the Tokens screen.

NOTE: The type of the tokens imported will be the one specified on OATH Policies screen. Please ensure that the type is correct before importing new tokens.

OATH Users

Swivelsecu	ire
Status	OATH / OATH Users 🚱
Log Viewer	OATH / OATH OSETS
Server	Total number of users: 0
▶ Policy	iotal number of users.
► Logging	Users per page: 50
Messaging	Search by username:
▶ Database	
▶ Mode	Search by serial ID:
▶ Repository	Search
▶ RADIUS	
Migration	
Appliance	Username Allocated Token Event Count
▼ OATH	
 OATH Policies 	
 OATH Tokens 	
OATH Users	
Config Sync	
Reporting	
User Administration	
Save Configuration	
Upload Email Images	
Administration Guide	
Logout	

This screen allows you to assign tokens to users that have been synced into the Swivel database. Search functionality enables you to filter the list by username or token serial ID. You can resynchronise the token count for those tokens that are assigned to users.

- Search: Allows you to filter the tokens by serial ID and/or username.
 Tokens per page: Allows you to specify the number of tokens displayed per page.

- Search by serial ID: Returns the tokens which contain the specified value in the serial ID.
- Search by username: Returns the tokens which contain the specified value in the username of the user assigned to the token.
- Assign Token: This button appears against tokens that are unallocated and it allows you to assign a token to a user. When you click the
 button, a new screen appears that presents a list of unallocated token Serial IDs for you to select from.
- Un-assign: When a user has a token allocated, this button appears in the corresponding row. Also allows you to un-assign the current token's user.
- Re-sync: This button appears against tokens that are allocated to a user and it allows you to resynchronise the current user's token. When you click the button, a new screen appears that presents two 'One Time Password' fields. Enter a One Time Password from the token in the first field, retrieve the next One Time Password from the Token and enter this into the second field. Press OK to re-sync the token.

Τ

OATH Assign Token



<u>Status</u>	OATH Assi	gn toke	en 🕑	
Log Viewer		-		
Server	User :	test4		
Policy	Total number of tol			
Logging	Tokens per page :	50		
Messaging	Search by serial ID	:		
Database		Searc	h	
Mode	Serial ID			
	1000302109374	Select		
RADIUS	1000502109574	Select		
Migration	1000302109373	Select		
Appliance	1000302109372	Select		
E OATH				
OATH Policies OATH Tokens	1000302109371	Select		
OATH Users	1000302109370	Select		
Config Sync				
Reporting	1000302109364	Select		
<u>User Administration</u>	1000302109363	Select		
<u>Save Configuration</u>	1000302109362	Select		
<u>Upload Email Images</u>				
<u>Administration Guide</u>	1000302109361	Select		
• Logout	1000302109360	Select		
	25			

This screen allows you to assign a token to a user and search tokens by serial ID. It only displays tokens which have not been allocated to a user.

- Search: Allows you to filter the tokens by serial ID.
- Tokens per page: Allows you to specify the number of tokens displayed per page.
- Search by serial ID: Returns the tokens which contain the specified value in the serial ID.
- Select: Assigns the token to the current user and returns to the OATH Users screen.